



Quick Start Guide for Remote Sites

RemotePoll™ version 1.2.0.9259

RemotePoll

Technical Requirements

- Requires a 2008 licensed RF or IR Receiver.
- Office XP, 2003, or 2007
- Intel or AMD 600 MHz class processor (1 GHz or higher recommended)
- 256 MB RAM
- 10 MB hard disk space (an additional 32 MB is required if you do not have Microsoft)
- .NET Framework 2.0 installed)
- 1024x768 resolution at 32-bit colour or higher
- Standard USB 1.1/2.0 port
- Ethernet or 802.11 compatible wireless network card
- Internet connection
- ResponseWare Session ID

Installing RemotePoll

1. Navigate to the downloads page on www.keepad.com (Support/Downloads/TurningPoint).
2. Select **RemotePoll**. (Note: RemotePoll is only available for PC).
3. Complete the software download registration form then click on **Download**.
4. Click on the link to start downloading **RemotePoll**.
5. A file download window will appear, click on **Save** then browse to a suitable location on your computer and click **Save** to start the download.
6. When the download is complete, double-click the "**setup**" icon to start the installation.
7. Select "**Run**" to start the InstallShield Wizard.
8. A welcome screen will appear on the InstallShield wizard, click **Next** to continue.
9. If you accept the terms of the License Agreement, select the button labelled **I accept the terms in the license agreement**. Then click **Next**.
10. Enter your User Name and Organisation in the customer information window and click **Next** to continue.
11. Click **Install**, to complete the installation.
12. When the installation is complete select **Launch RemotePoll** if you would like to immediately open the program.
13. Click **Finish** to exit the wizard.

Updated 1st December 2009

Hardware Setup

1. **Connect** your TurningPoint 2008 licensed RF or IR Receiver.
2. **Launch** RemotePoll by clicking on the RemotePoll icon on the desktop.

NOTE: TurningPoint must be closed before RemotePoll is opened.
3. **Click** the Settings tab.
4. For RF receivers, select the **Radio Frequency channel** number from the drop-down menu next to the receiver. (The default channel is 41).
 - For IR receivers, verify that the receiver serial number is listed.
5. **Select** the Polling Test tab.
6. Click the **Start Test** button (bottom right).
7. Press a key on each ResponseCard and verify the response is received in the polling test window.
8. Click the **End Test** to close the Polling test.

Configuring RemotePoll to connect to the Host Computer

1. **Select** the Status tab.
2. **Enter** the Session ID number (as supplied by the RemotePoll Presenter/ Host).
3. **Click** on the ResponseWare connect button.
RemotePoll is now connected and will send all responses to the presenting computer. The current status will be displayed in the RemotePoll Message Log. If a question is currently being polled, the question text along with response choices will appear in this portion of the RemotePoll application.

Repeat the above steps on all machines that are joining remotely.

NOTE: A video conferencing system or desktop sharing application is required to display the presentation with the TurningPoint questions. Without this, the participants at the remote site/s will not be able to view the TurningPoint questions.

Contact Us

For further information please contact our customer support specialists.

Freecall within Australia: 1800 463 279

International: +61 7 3440 8000

Via email: support@keepad.com

Via web: www.keepad.com

